

Brainware Intelligent Capture

Installation Guide

Version: Foundation EP1

Written by: Documentation Team, R&D

Date: Tuesday, January 14, 2025

Copyright

Information in this document is subject to change without notice. The software described in this document is furnished only under a separate license agreement and may be used or copied only according to the terms of such agreement. It is against the law to copy the software except as specifically allowed in the license agreement. This document or accompanying materials contains certain information which is confidential information of Hyland Software, Inc. and its affiliates, and which is subject to the confidentiality provisions agreed to by you.

All data, names, and formats used in this document's examples are fictitious unless noted otherwise. Complying with all applicable copyright laws is the responsibility of the user. Without limiting the rights under copyright law, no part of this document may be reproduced, stored in or introduced into a retrieval system, or transmitted in any form or by any means (electronic, mechanical, photocopying, recording, or otherwise), or for any purpose, without the express written permission of Hyland Software, Inc. or one of its affiliates.

Hyland® and Hyland Software®, as well as Hyland product names, are registered and/or unregistered trademarks of Hyland Software, Inc. and its affiliates in the United States and other countries. All other trademarks, service marks, trade names and products of other companies are the property of their respective owners.

© 2020 Hyland Software, Inc. and its affiliates. All rights reserved.

Table of Contents

About Brainware Intelligent Capture	8
<i>Brainware API</i>	8
<i>Prerequisites</i>	8
<i>About the Brainware Intelligent Capture Process</i>	9
<i>About the Brainware Intelligent Capture Database</i>	10
Install Brainware Intelligent Capture	10
<i>Download the Setup Package</i>	11
<i>About the Complete and Custom Installation Types</i>	11
<i>About Help Files</i>	11
HelpLink Parameters	11
Modify SetupType.ini for Help	12
<i>Verify SQL Server Permissions</i>	12
<i>Preparations for the Installation of an Oracle Database</i>	13
Create the Tablespace	13
Create the Database User	13
<i>Install BIC Attended</i>	14
<i>Install BIC Unattended</i>	15
Silent Install.ini Parameters	16
[General]	16
[Applications]	17
[OCR Engines]	17
[Additional]	18
[AutoServiceUpdate]	18
[Database Configuration]	19
[DB Credentials]	19
<i>Install an Additional Runtime Server Instance</i>	20
<i>Brainware Intelligent Capture Subdirectories</i>	20
<i>Modify the Application-Specific HelpLink Parameters</i>	20
<i>CONFIG Files</i>	21
<i>Install the Database Manually</i>	21

Create the SQL Server Database	21
Create the Oracle Database	22
Modify the Database Connection Strings	22
Revoking Oracle User Rights	24
Components Version Info Tool	24
<i>Components General Info View</i>	24
<i>Components Licensing Info View</i>	24
<i>Review the Installed Components</i>	25
<i>Review the Component License Information</i>	25
Manage the BIC Components	25
<i>Add or Remove BIC Components</i>	25
<i>Manually Register Components</i>	26
About the Brainware Intelligent Capture Core Service	26
Configuration for Web Verifier	26
<i>Configure IIS for Web Verifier</i>	27
Role Services Configuration for Web Verifier in IIS 7.5 and Above	27
Common HTTP Features	27
Application Development	27
Health and Diagnostics	27
Create the Application Pool for Web Verifier in IIS 7.5 and Above	27
Configure Web Verifier in IIS 7.5 and Above	28
Configure a White Label Directory in IIS	28
<i>Configure Web Verifier</i>	28
Modify the instanceName Value When Using Multiple Web Servers	29
Modify the Database Connection Strings for Web Verifier	29
<i>Configure Server Security for Web Verifier</i>	30
Add the User Context in SQL Server	30
Verify the IIS Identity	30
Set Permissions for BIC Projects	31
Set Permissions for BIC Bin Directory	31
<i>Configure Internet Explorer for Web Verifier</i>	31
<i>Implement Single Sign-On Authentication</i>	32

About the Single Sign-On Authentication for Web Verifier	32
Enable the Single Sign-On Authentication	32
About the Single Sign-On Session and the Web Verifier Session	32
Modify the Web Verifier Session Timeout	33
<i>Configure Windows Authentication</i>	33
About Windows Authentication for Web Verifier	33
Configure Windows Authentication in IIS 7.5 and Higher	33
Create a Windows Authentication Version of the Web.config File	33
Switch Back to Forms Authentication	34
<i>Configure Cookies for Web Verifier</i>	34
<i>About Web Verifier Performance</i>	35
Image Conversion	35
Remote Matching Service	35
Delayed Validation	35
<i>Use Traditional Chinese</i>	35
<i>Access Web Verifier</i>	36
<i>Additional Columns in Verifier or Web Verifier</i>	36
Display and Name Additional Verifier Columns: SQL Server	36
Display and Name Additional Verifier Columns: Oracle	37
Display Additional Web Verifier Columns	37
Change the Web Verifier Column Names	38
Configure Global Application Settings	38
<i>About Workflow History Reporting</i>	38
Configure Workflow History Reporting: SQL Server	38
Configure Workflow History Reporting: Oracle	39
<i>About Disabling Batch Deletion in Runtime Server and Designer</i>	40
Disable Batch Deletion: SQL Server	40
Disable Batch Deletion: Oracle	40
<i>About Modifying the URL Expiration Time for Web Verifier</i>	40
Modify the URL Expiration Time: SQL Server	40
Modify the URL Expiration Time: Oracle	41
Configure BIC Security	41
<i>File System Security</i>	41

<i>Recommended Accounts and Groups</i>	43
<i>Configure Access to Project Data</i>	44
<i>About the Service Account on a Domain Network</i>	44
<i>About the Service Account for System Monitoring</i>	45
<i>About the Service Account for Email Importing</i>	45
<i>About INI File Encryption</i>	45
<i>Encrypt a Password for a Database Connection String</i>	45
<i>About User Password Encryption</i>	46
Change the Hashing Algorithm	46
Configure BIC Runtime Components	47
<i>About RTS Remote Administration MMC</i>	47
<i>Configure the Runtime Service Manager Service</i>	47
<i>Configure the RTS Remote Administration MMC Snap-In</i>	48
<i>Configure the Email Import Feature in Microsoft Outlook</i>	48
About the Desktop Heap Size	49
<i>Modify the Desktop Heap Size</i>	49
<i>Ideal Desktop Heap Size</i>	50
About Logging	50
<i>Log Files</i>	51
<i>Logging Levels</i>	52
<i>Configure the Logging Level</i>	53
<i>Configure the Location of the Application Log Files</i>	53
<i>Configure the Retention Time of Application and Error Log Files</i>	54
OCR Engine Languages	54
<i>Available OCR Engines</i>	55
Cleq Barcode Engine	55
FineReader10 OCR Engine	55
FineReader11 OCR Engine	56
CloudOCR Engine	56
Kadmos 5 OCR Engine Client Edition	56
Kadmos 5 OCR Engine Server Edition	56
QualitySoft Barcode Engine	56
About Automated Update	56

<i>Modify the Batch File</i>	57
<i>Modify the Application Shortcuts for Verifier and Designer</i>	57
<i>Automate Runtime Server Updates</i>	57
About Port Configuration	58
<i>Configure a Different Port for Runtime Server</i>	58
File Permission Matrix	58
Web.config Options and Associated Resource File Parameters	62
<i>About Navigation to Documents for Indexing</i>	69
Example	69
<i>Enable Navigation to Indexable Documents</i>	69
Registry Options	70
<i>Create the Registry Key ErrorTraceDir</i>	70
<i>Create the Registry Key HideBatchReleaseDialog</i>	71
<i>Modify the Registry Key ErrorTrace - All</i>	71
<i>Create the Registry Key MaximumDiskSpaceUsageMB</i>	71
<i>Create the Registry Key TotalDaysToKeepFiles</i>	72

About Brainware Intelligent Capture

Brainware Intelligent Capture (BIC) is a document processing system.

It combines optical character recognition (OCR), automatic data extraction from any document type, and validation of that data against known data sources for auto-processing to your ECM system and other core business applications.

Brainware Intelligent Capture includes the following applications.

- Brainware Intelligent Capture Designer
- Brainware Intelligent Capture Runtime Server
- Brainware Intelligent Capture Verifier
- Brainware Intelligent Capture Web Verifier

For information about the document processing system, see [About the Brainware Intelligent Capture Process](#).

Brainware API

The Brainware Intelligent Capture setup package includes the Brainware API installation files.

For more information, see the *Brainware API Installation Guide*.

Prerequisites

To verify your system requirements and database meet the minimum requirements for BIC, refer to the *Brainware Intelligent Capture Technical Specifications*. Before you install BIC, verify the following prerequisites.

- Ensure that you have local administrator rights and access to the Windows registry.
- Enable VBScript execution.
- Verify that you have installed Internet Information Services (IIS) on your server if your installation will include Web Verifier.
- If you use Oracle as a database, install a 32-bit Oracle client on any workstation or server where BIC communicates with the database, such as when using Designer or Verifier.
- Create the users and groups if you use the Microsoft-recommended resource rights assignment model.

About the Brainware Intelligent Capture Process

Brainware Intelligent Capture (BIC) analyzes text from any media type. It uses artificial neural network techniques to automatically classify structured and unstructured documents and extract meaningful information from them. Once a sample based learning method is employed BIC can handle information that is similar to the samples without programming or extensive rule setting. BIC can operate at high speed and can be implemented on parallel hardware to further enhance performance.

BIC forms a complete document processing system, as illustrated in the diagram below



First, using capture, documents come into the process from a variety of sources.

Next, BIC recognizes all eligible data values on the page.

Then, BIC uses the extracted data to sort and classify the documents. Based on the document type, BIC extracts field-level and line item level data. It does this without templates, anchors, keywords or zones.

Finally, BIC can validate extracted data against your business application data to ensure accuracy before exporting it for workflow processing.

About the Brainware Intelligent Capture Database

The BIC installation process allows you to create the required database on your Microsoft SQL Server server during the installation. You can also create the database manually after the BIC installation procedure. If using an Oracle database server, the database must be created manually.

BIC stores the following data in the database.

- Documents
- Batches
- Project references
- Web Verifier configuration
- Batch and document lock handling
- Users, groups, roles, and relationships
- Application level user licensing

Install Brainware Intelligent Capture

To install BIC, complete the following procedures.

- [Download the Setup Package](#)
- Optional. [Modify the help file location](#)
- Optional. Complete one of the following substeps to verify database permissions.

Note:

To create the database during BIC installation, you must have user credentials which have the proper permissions.

- [Verify SQL Server permissions](#)
- [Verify Oracle permissions](#)
- [Install BIC Attended](#) or [Install BIC Unattended](#)
- Optional. [Modify the Application-Specific HelpLink Parameters](#)
- If you did not install the database with the installation wizard, complete the steps in [Install the database manually](#).
- Optional. [Encrypt the password for a database connection string](#).
- Copy the license file. For more information, see "Copy the license file to local license directories" in the *Brainware Intelligent Capture Product Licensing Guide*.
- [Configure Internet Information Services](#) and [Web Verifier](#), if the installation includes Web Verifier

- [Configure BIC Security](#)
- [Configure BIC Runtime Components](#)

Download the Setup Package

To obtain Perceptive product installation files, complete the following steps.

1. Contact the Hyland Software Technical Support group.
For a list of Technical Support phone numbers, go to www.hyland.com/pswtscontact.
2. Save and unzip the installation files locally so you can access them during installation.

About the Complete and Custom Installation Types

When you install BIC with an attended installation, you choose a complete or a custom installation type.

The complete option installs Designer, Runtime Server, Verifier and Web Verifier in the *[drive:]\[Program directory]\[Installation directory]* and creates the Brainware Intelligent Capture program group. It also installs the following recognition engines.

- FineReader 10
- FineReader 11
- Kadmos 5
- QualitySoft

The custom installation type allows you to choose which applications, demo projects, and recognition engines you want to install. It also lets you select which programs you want to update automatically.

About Help Files

By default, the Brainware Intelligent Capture products provide hosted product help, which enables you to always access the most recent information directly from the documentation website. If your company's network security does not allow users to open a URL, you can download static help through the Customer Portal. To implement static help instead of hosted help, you must modify the configuration.

The SetupType.ini file enables you to specify the path and file that the BIC application opens when you click Help in the Help menu of a particular product. You can place the files on a web server and specify the URL to the file that launches Help for that product or you can unzip the files on a local or a server drive, and use that file path.

HelpLink Parameters

You can redirect product help from the default web URLs to a file on your system.

The HelpLink variable is a label that applies to a particular product. The products that provide help include: Designer, RTS, Verifier, Learnset Manager, and Web Verifier.

The syntax includes the HelpLink type, which defines the product, and the path to the static file location.

```
HelpLink = [path]/PIC.htm#Foundation_EP1
```

```
HelpLink_Designer = [path]/PICD.htm
```

```

HelpLink_RTS = [path]/PICRS.htm
HelpLink_Verifier = [path]/PICV.htm
HelpLink_LSM = [path]/PICV.htm#Topics/Verifier/Working with the Learnset
Manager.htm
HelpLink_WebVerifier = [path]/PICWV.htm

```

For path, supply the URL or path (absolute or relative) to the launch file for that specific help project. The following examples show a URL, a network path, and a local path.

- HelpLink_Designer = https://docs.mycompany.com/mypath/Designer/PICD.htm
- HelpLink_Designer = \\myserver\mypath\Designer\PICD.htm
- HelpLink_Designer = C:/mypath/Designer/PICD.htm

Modify SetupType.ini for Help

To modify the SetupType.ini file, complete the following steps.

1. From the setup directory, open the **SetupType.ini** file with a text editor.
2. In the **SetupType.ini** file, in the [Help] section, specify the path for each HelpLink. The following lines show sample URLs to the hosted documentation.

Example

```

HelpLink_Designer =
https://docs.mycompany.com/mypath/Designer/PICD.htm

HelpLink_RTS = https://docs.mycompany.com/mypath/Runtime_
Server/PICRS.htm

HelpLink_Verifier =
https://docs.mycompany.com/mypath/Verifier/PICV.htm

HelpLink_WebVerifier = https://docs.mycompany.com/mypath/Web_
Verifier/PICWV.htm

```

3. Save and close the file.

Verify SQL Server Permissions

To use BIC with a SQL Server database, verify that your account has the following rights.

Note: You can use Windows authentication if the user performing the installation has the appropriate rights to the database server.

- Rights to create, modify, and delete tables.
- Rights to add, modify, and delete data.

Preparations for the Installation of an Oracle Database

Create the Tablespace

A default tablespace and a temporary tablespace are required to create the BIC user and the schema. Complete the following steps.

1. Create the default tablespace according to the following example.

Example

```
CREATE TABLESPACE BIC
  DATAFILE 'bic.dat'
  SIZE 20M AUTOEXTEND ON;
```

2. Create the temporary tablespace according to the following example.

Example

```
CREATE TEMPORARY TABLESPACE T_BIC
  TEMPFILE 'temp_BIC.dbf'
  SIZE 5M AUTOEXTEND ON;
```

Create the Database User

To create the database user, complete the following steps.

Prerequisite

- The user needs a login, in the example 'IDENTIFIED BY PASSWORD'
If you want to use a different authentication type, see the Oracle documentation for more information.
- The user needs an unlimited quota on the default tablespace.

1. Create a user with password authentication according to the following example.

Note: The user name must be written in capital letters.

Example

```
CREATE USER BIC
  IDENTIFIED BY <password>
  DEFAULT TABLESPACE BIC
  TEMPORARY TABLESPACE T_BIC
  QUOTA UNLIMITED ON BIC;
```

2. Grant the user the permissions required to create database objects according to the following example.

Example

```
GRANT
```

```

CONNECT,
CREATE SESSION,
CREATE TABLE,
CREATE TYPE,
CREATE INDEXTYPE,
CREATE PROCEDURE,
CREATE SEQUENCE,
CREATE SYNONYM,
CREATE PUBLIC SYNONYM,
CREATE TRIGGER
TO BIC;

```

Install BIC Attended

To install BIC, complete the following steps.

1. Run **setup.exe**.

Note: The installation process is available in English and German. The language used depends on the regional settings of your system. The default language is English.

2. If .NET Framework 4.6 is not installed, complete one of the following substeps.
 - To allow setup.exe to install .NET Framework 4.6, select **Let the setup install .NET Framework Version 4.6 (Recommended)** and then click **Next**.

Note:

The .NET Framework installer automatically restarts the computer without further notification.

- To cancel the setup and install the required .NET Framework manually, select **Abort setup** and then click **Next**. After installing .NET Framework, rerun **setup.exe** and proceed with the following steps.
3. In the **Setup Hyland Brainware Intelligent Capture** page, click **Next**.
 4. In the **License Agreement** page, read and accept the End-User License Agreement (EULA), and then click **Next**.
 5. In the **Installation Type** page, select **Complete** or **Custom** and click **Next**.
 6. If you selected **Custom**, complete the following substeps. If you selected **Complete**, continue to the next step.
 1. In the **Installation Directory** page, accept the default or change the directory, and then click **Next**.
 2. In the **Feature Selection** page, clear any unrequired applications, demo projects, and recognition engines and then click **Next**.
 3. Optional. In the **Configuration of Auto Update Feature** page, select the programs you want to update automatically.
 4. The following option is currently not in use: Optional. In the **Shared network updates**

directory field, type or browse to a path.

Note: The path must exist. The installation process uses this path to create and configure the batch files required for the automated update feature.

5. Click **Next**.
7. In the **Program Folder** page, accept the default program directory or select one of the existing directories and then click **Next**.
8. In the **Selected Install Options** page, verify your selections and then click **Next**.
9. In the **WIBU-KEY Runtime-Kit** dialog box, click **Yes**.
10. In the **Database Setup Options** page, select one of the following options and then click **Next**.
 - SQL Server
 - Oracle
 - Do not install database

Note: The Oracle option is not available. To create an Oracle database, please refer to the manual instructions.

11. For SQL Server, complete the following substeps.
 1. In the **Login Credentials** page, either select **Windows Authentication** or type the user ID and password and then click **Next**.
 2. In the **Database Server Information** page, in the **Database Server Name** field, type the database server name and then click **Next**.
12. In the **Performed Tasks** page, click **Next**.
13. Optional. In the **Icons on Desktop** page, select **Create desktop shortcuts for applications** and click **Finish**.

Install BIC Unattended

To install BIC on several machines concurrently, such as Verifier workstations, use the silent installation mode. To install BIC silently, complete the following steps.

1. From the *[drive:]\[setup directory]* directory, open the **Silent Install.ini** file with a text editor.
2. In the **Silent Install.ini** file, change the parameters according to your needs.

Note: You can delete single parameters or complete sections, but you cannot move a parameter outside of its appropriate section.

3. Save and close the file.
4. From the *[drive:]\[setup directory]* directory, execute the **setupsilent.bat** file.

Silent *Install.ini* Parameters

The following topics describe the parameters available in the Silent Install.ini file.

- [\[General\]](#)
- [\[Applications\]](#)
- [\[OCR Engines\]](#)
- [\[Additional\]](#)
- [\[AutoServiceUpdate\]](#)
- [\[Database Configuration\]](#)
- [\[DB Credentials\]](#)

[General]

This section contains general installation parameters.

Path

The installation path, without a trailing backslash.

Example

```
Path = C:\Program Files\YourCompanyName
```

EULA

End-user license agreement The following values are recognized:

“Accepted”

“Not Accepted”: Default value - the silent installation cancels.

MoveComponentsIfRequired

Indicates whether to use the existing component directory or to move any previous components to the new BIC directory prior to installation.

0: Use existing component directory.

1: Default value – Move components to the new directory.

CreateDeskTopIcons

0: Default value – do not create desktop shortcuts.

1: Create desktop shortcuts.

InstallWibuKey

0: Skip WIBU-key driver installation.

1: Default value - install WIBU-key drivers

StopIfDotNetIsNotFound

Web Verifier and the database connections require .NET Framework.

0: If the required .NET Framework is not present, the installation proceeds and automatically installs the required version.

1: Default value - Cancel the installation if the required .NET Framework version is not present.

[Applications]

Defines which applications to install. To install only the extraction components, set all parameters in this section to 0.

Designer

0: Do not install Designer

1: Default value – Install Designer

Verifier

0: Do not install Verifier

1: Default value – Install Verifier

Runtime Server

0: Do not install Runtime Server

1: Default value – Install Runtime Server

Web Verifier

0: Do not install Web Verifier

1: Default value – Install Web Verifier

[OCR Engines]

Defines which OCR engines to install.

FineReader10

0: Do not install the FineReader10 engine

1: Default value – Install FineReader10 engine

FineReader11

0: Do not install the FineReader11 engine

1: Default value – Install FineReader11 engine

Kadmos5

0: Do not install the Kadmos 5 engine

1: Default value – Install Kadmos 5 engine

Cleqs

0: Do not install the Cleqs engine

1: Default value – Install Cleqs engine

QualitysoftBarcode

0: Do not install the QualitySoft engine

1: Default value – Install QualitySoft engine

[Additional]

Additional files to install.

Demo Files

0: Do not install the demo project files

1: Default value – Install the demo project files

[AutoServiceUpdate]

Defines whether the automatic service update feature installs.

ForDesigner

0: Default value – Do not define an automatic service update for Designer.

1: Define an automatic service update for Designer.

ForVerifier

0: Default value – Do not define an automatic service update for Verifier.

1: Define an automatic service update for Verifier.

NetworkUpdateFolder

The path where the automatic service update will look for updates.

The default value is an empty string.

[Database Configuration]

Settings for an existing database server.

DBServerType

- 1: Configure the SQL Server database
- 2: Not functional
- 3: Default value – Do not configure a database

UseDBConfIniFile

Path and filename of a text file that contains the database connection string.

The default value is an empty string. If you do not define a file, the installer uses the credentials in the [DB Credentials] section. If the [DB Credentials] section does not exist, the DBServerType parameter defaults to 3.

[DB Credentials]

You can use this section instead of defining a file in the parameter UseDBConfIniFile.

Note: The database configuration skips, if the parameter UseDBConfIniFile contains an empty string.

The following options apply for SQL Server connections only.

SQLServerWindowsAuthent

- 0: Default value – Do not use Windows authentication for database access
- 1: Use Windows authentication for database access

SQLServerAdminUser

The DBA account name. The default value is an empty string.

SQLServerAdminPassword

The DBA account password. The default value is an empty string

DBUserWindowsAuthent

- 0: Default value – Do not use Windows authentication for database user
- 1: Use Windows authentication for the database user

DBUserName

The database user account name. The default value is an empty string.

DBUserPassword

The database user account password. The default value is an empty string.

DatabaseServerPath

The database name in the format *<MachineName>\<InstanceName>*. The default value is an empty string.

Install an Additional Runtime Server Instance

To install an additional Runtime Server instance and connect it to an existing database, complete the following steps.

1. Install BIC without installing the database.
2. Copy the following configuration files from an existing installation to the new installation directory.
 - *[Installation path]*\Brainware Intelligent Capture Web Server\Web.config
 - *[Installation path]*\Brainware Intelligent Capture\bin\DstDsr.exe.config
 - *[Installation path]*\Brainware Intelligent Capture\bin\DstHost.exe.config
 - *[Installation path]*\Brainware Intelligent Capture\bin\DstSIm.exe.config
 - *[Installation path]*\Brainware Intelligent Capture\bin\DstVer.exe.config
 - *[Installation path]*\Brainware Intelligent Capture\bin\DstCoreSvc.exe.config
 - *[Installation path]*\Brainware Intelligent Capture\bin\DstWkBrw.exe.config

Brainware Intelligent Capture Subdirectories

Setup creates the following subdirectories in the installation directory.

- \Components\Bwe contains the BIC Toolkit.
- \Components\Cairo contains the license file and the base components for imaging and recognition.
- \Components\Cedar contains the base components for document analysis.
- \Components\Tools contains the installation log file as well as several tools and utilities for BIC, such as the SCBLibVersion.exe component version information tool
- \Brainware Intelligent Capture\bin contains the BIC executables and the settings files.
- \Brainware Intelligent Capture\bin\LogRoot\Log contains the log files.
- \Brainware Intelligent Capture Web Server contains the BIC web components, the Web.config file, and other web libraries used by Web Verifier.
- \Projects contains demo projects.

Modify the Application-Specific HelpLink Parameters

You can modify the application-specific HelpLink parameters if required. Complete the following steps.

1. From *[Installation path]*\Brainware Intelligent Capture\bin, open the required configuration file, such as **DstDsr.exe.config** for Designer, in a text editor.
2. Search for the following line.


```
<add key="HelpLink"
```

3. Modify the `value` parameter according to your needs.

CONFIG Files

The following table provides a list of the CONFIG files used by the BIC applications.

Application	CONFIG files
Designer	<i>[Installation path]</i> \Brainware Intelligent Capture\bin\DstDsr.exe.config
Learnset Manager	<i>[Installation path]</i> \Brainware Intelligent Capture\bin\DstSlm.exe.config
Runtime Server	<i>[Installation path]</i> \Brainware Intelligent Capture\bin\DstHost.exe.config
Verifier	<i>[Installation path]</i> \Brainware Intelligent Capture\bin\DstVer.exe.config
Core Service	<i>[Installation path]</i> \Brainware Intelligent Capture\bin\DstCoreSvc.exe.config
Workdoc Browser	<i>[Installation path]</i> \Brainware Intelligent Capture\bin\DstWkBrw.exe.config
Web Verifier	<i>[Installation path]</i> \Brainware Intelligent Capture Web Server\Web.config
Supervised Learning in Web Verifier	<i>[Installation path]</i> \Brainware Intelligent Capture\bin\Brainware.System.Project.exe.config

Install the Database Manually

If you did not install the database with the installation wizard, you can execute the scripts manually. Complete the following steps.

1. Complete one of the following substeps.
 - [Create the SQL Server Database.](#)
 - [Create the Oracle Database.](#)
2. [Modify the database connection strings.](#)

Create the SQL Server Database

To create the SQL Server database, complete the following steps.

1. Launch the **SQL Server Management Studio**.
2. Log in using an account with administrator rights.
3. Create a new database with a meaningful name, such as **Brainware Intelligent Capture**.
4. From the *[drive:]**[setup directory]*\FirstPart\Database\CreationScripts\SQL Server directory, execute the **BrwCreateDatabase.sql** script.

5. From the **[drive:]/[setup directory]\FirstPart\Database\UpdateScripts\SQL Server** directory, execute the **BRW_Upgrade_Database.sql** script against the BIC database.
6. Review the **Messages** pane for errors.

Note: If there are errors, you can rerun the script as often as required.

Create the Oracle Database

We recommend creating the BIC database in a separate schema which is not shared with any other programs. To execute the creation scripts, use the owner of the schema created for BIC. Complete the following steps.

1. To execute the installation scripts using **SQL Developer**, complete the following substeps.
 1. Configure a connection for the BIC user.
 2. From the **[drive:]/[setup directory]\FirstPart\Database\CreationScripts\Oracle** directory, open the **BrwCreateDatabase.sql** script.
 3. Ensure that the connection is set to the BIC user and then execute the script.
 4. From the **[drive:]/[setup directory]\FirstPart\Database\UpdateScripts\Oracle** directory, open the **BRW_Upgrade_Database.sql** script.
 5. Ensure that the connection is set to the BIC user and then execute the script.
2. To execute the installation scripts using **SQL Plus**, complete the following substeps.
 1. Start **SQL Plus** and connect to the database as the BIC user.
 2. From the **[drive:]/[setup directory]\FirstPart\Database\CreationScripts\Oracle** directory, execute the **BrwCreateDatabase.sql** script.
 3. From the **[drive:]/[setup directory]\FirstPart\Database\UpdateScripts\Oracle** directory, execute the **BRW_Upgrade_Database.sql** script.

Modify the Database Connection Strings

To modify the database connection strings for all BIC components, except Web Verifier, complete the following steps.

Note: To modify the database connection strings for Web Verifier, see “Modify the database connection strings for Web Verifier”.

1. From the **[Installation path]\Brainware Intelligent Capture\bin** directory, open **DstDsr.exe.config** in a text editor.
2. Search for the `<connectionStrings>` element.

Note:

For information about password encryption, see [Encrypt the password for a database connection string](#).

3. For a SQL Server database, modify the following values.
 - Set Data Source.

- Set Initial Catalog to the SQL Server database catalog.
- Set User ID to the SQL Server user ID.
- Set Password to the SQL Server password.

Example

```
<connectionStrings>
<add name="Entities"

connectionString="metadata=res://*/Entity.Entities.csd|res://*/Entity
.Entities.ssd|r
es://*/Entity.Entities.msl; provider=System.Data.SqlClient;provider
connection
string=&quot;Data Source=<DataSource>;Initial
Catalog=<SQLServerDatabaseCatalog>;Integrated Security=false;User
ID=<UserId>;Password=<UserPassword>;MultipleActiveResultSets=True&quo
t;"
providerName="System.Data.EntityClient" />
</connectionStrings>
```

Note: To copy the connections string example as a single line, open this document in Acrobat Reader and copy and paste the string from there.

4. For an ORACLE database, modify the following values.
 - Set Data Source.
 - Set User ID to the service account user ID.
 - Set Password to the service account password.

Example

```
<connectionStrings>
<add name="Entities"

connectionString="metadata=res://*/Entity.ORAEntities.csd|res://*/Ent
ity.ORAEntities.
ssdl|res://*/Entity.ORAEntities.msl; provider=EFOracleProvider;
Provider Connection
String='Data Source=<OracleServerName\InstanceName>;User
ID=<UserID>;Password=<UserPassword>' "
providerName="System.Data.EntityClient" />
</connectionStrings>
```

Note: To copy the connections string example as a single line, open this document in Acrobat Reader and copy and paste the string from there.

5. Save and close the file.

6. Repeat the previous steps for the following configuration files.
 - DstVer.exe.config
 - DstHost.exe.config
 - DstSlm.exe.config
 - DstCoreSvc.exe.config
 - Brainware.System.Project.exe.config
 - DstWkBrw.exe.config

Revoking Oracle User Rights

After creating or updating the Oracle database, you can revoke some of the permissions from the BIC user because they are no longer needed. Complete the following step.

- Revoke the permissions according to the following example.

```

REVOKE
  CREATE TYPE,
  CREATE INDEXTYPE,
  CREATE PROCEDURE,
  CREATE SEQUENCE,
  CREATE SYNONYM,
  CREATE PUBLIC SYNONYM,
  CREATE TRIGGER
FROM BIC;

```

Components Version Info Tool

The Components Version Info tool provides information about the installed DLLs and the components that require an entry in the license file to be available.

Components General Info View

This view lists the installed primary DLLs and provides the following information.

See also: [Review the Installed Components](#).

- Name. Name of the installed DLL.
- Description. Description of the DLL.
- Build. Build number of the DLL.
- Product version. Version of the DLL.
- Date. Compilation date and time.
- Build Date Time. Date and time the build was created.
- Install Directory. Path to the component location.

Components Licensing Info View

This view lists licensable components and provides the following information.

See also: [Review the Component License Information](#).

- Component Name. Name of the component.
- Component Type. Type of the component.
- Status. License status of the component.
- License File Path. License file location.
- License Files. License file name.
- Expires. License expiration date for component.
- Version. Version number.
- Customer. Customer name.
- Customer ID. Customer ID.
- Serial. Serial number.

Review the Installed Components

To review the installed components, complete the following steps.

1. Start the **Components Version Info** tool.
2. To display the list of installed components, click **View > Components General Info**.
3. Optional. To copy the displayed information to the clipboard, click **File > Copy to Clipboard**.
4. Optional. To save the displayed information to a file, click **File > Save to File**.

Review the Component License Information

To review the component license information, complete the following steps.

1. Start the **Components Version Info** tool.
2. To display the license information, click **View > Components Licensing Info**.

Manage the BIC Components

The BIC installation process enables you to add or remove the following components.

- Brainware Intelligent Capture Designer
- Brainware Intelligent Capture Runtime Server
- Brainware Intelligent Capture Verifier
- Brainware Intelligent Capture Web Verifier

Add or Remove BIC Components

To modify an existing Brainware Intelligent Capture installation and to add or remove components, complete the following steps.

1. From **Windows Programs and Features**, select **Brainware Intelligent Capture** and then click **Change**.
2. In the **License Agreement** page, read and accept the End-User License Agreement (EULA), and then click **Next**.

3. In the **Setup** page, select **Modify** and then click **Next**.
4. In the **Feature Selection** page, select or clear the desired components and then click **Next**.
5. In the **Icons on Desktop** page, complete the following substeps.
 1. Optional. Select **Create desktop shortcuts for applications**.
 2. Click **Finish**.

Manually Register Components

The installation process automatically registers the Cro*.dll, Cdr*.dll, and Bwe*.dll components. For troubleshooting purposes, you can manually register these components. To register the components, complete the following steps.

1. From the *[Installation path]\Brainware Intelligent Capture\Components\Cairo* directory, execute the **RegCro.bat** file.
2. From the *[Installation path]\Brainware Intelligent Capture\Components\Cedar* directory, execute the **RegCdr.bat** file.
3. From the *[Installation path]\Brainware Intelligent Capture\Components\Bwe* directory, execute the **RegBwe.bat** file.

About the Brainware Intelligent Capture Core Service

The Brainware Intelligent Capture Core service is required for BIC's shared license management.

- The service runs as a Windows Service under the **Network Service** account by default.
- The **DstCoreSvc.exe.config** file contains the database connection string.
- The service starts automatically after installation and restarts according to the following rules.
 - The service restarts immediately if it stops working for the first time.
 - The service restarts after 10 seconds if it stops working for the second time.
 - The administrator must restart the service manually if it stops working for the third time on the same day.

Configuration for Web Verifier

Your Internet Information Server (IIS) executes Web Verifier. To configure IIS and Web Verifier, complete the following tasks as necessary.

- [Configure IIS for Web Verifier](#)
- [Configure Web Verifier](#)
- [Configure Server Security for Web Verifier](#)
- [Configure Internet Explorer for Web Verifier](#)
- Optional. [Implement single sign-on authentication](#)
- Optional. [Configure Windows Authentication](#)
- Optional. Configure SSL. For information on how to configure SSL on your IIS machine, refer to <http://support.microsoft.com>.
- Optional. [Configure Cookies for Web Verifier](#)

Configure IIS for Web Verifier

To configure IIS for Web Verifier, complete the following tasks.

- [Ensure that the required role services are enabled.](#)
- [Create the Application Pool for Web Verifier in IIS 7.5 and Above](#)
- [Configure Web Verifier in IIS 7.5 and Above](#)
- [Configure a White Label Directory in IIS](#)

Role Services Configuration for Web Verifier in IIS 7.5 and Above

Web Verifier requires the following role services in IIS.

Common HTTP Features

- Static Content
- Default Document
- Directory Browsing
- HTTP Errors

Application Development

- ASP.NET 4.6 (ASP.NET 4.5 for operating system earlier than Windows Server 2016)
- .NET Extensibility
- ISAPI Extensions
- ISAPI Filters

Health and Diagnostics

- HTTP Logging
- Request Monitor

Create the Application Pool for Web Verifier in IIS 7.5 and Above

To create the application pool for Web Verifier, complete the following steps.

1. Start **Internet Information Services (IIS) Manager**.
2. In the **Internet Information Services (IIS) Manager** window, in the left pane, right-click the local computer and then click **Switch to Content View**.
3. In the middle pane, right-click **Application Pools** and then click **Add Application Pool**.
4. In the **Add Application Pool** dialog box, complete the following substeps.
 1. In the **Name** field, type `WebVerifierPool`.
 2. From the **.NET CLR version** list, select **.NET CLR v4.0.30319** and then click **OK**.
5. In the left pane, click **Application Pools**.
6. In the middle pane, right-click **WebVerifierPool** and then click **Advanced Settings**.
7. In the **Advanced Settings** dialog box, provide the following settings and then click **OK**.

- Enable 32-Bit Applications = True
- Managed Pipeline Mode = Integrated
- Identity = ApplicationPoolIdentity

Note: Alternatively, you can specify a service account.

- Load User Profile = True

Configure Web Verifier in IIS 7.5 and Above

To configure Web Verifier in IIS 7.5 and above, complete the following steps.

1. Start **Internet Information Services (IIS) Manager**.
2. In the **Internet Information Services (IIS) Manager** window, in the left pane, expand **Sites > Default Web Site**.
3. Right-click **Default Web Site** and then click **Add Application**.
4. In the **Add Application** dialog box, complete the following substeps.
 1. In the **Alias** field, type `WebVerifier`.
 2. In the **Application pool** field, select the pool that was configured before, such as **WebVerifierPool**.
 3. In the **Physical path** field, type or browse to the **[Installation path]\Brainware Intelligent Capture Web Server** directory and then click **OK**.
5. In the **Internet Information Services (IIS) Manager** window, in the left pane, select **WebVerifier**.
6. In the middle pane, under **IIS**, double-click **Default Document**.
7. In the right pane, click **Add**.
8. In the **Add Default Document** dialog box, in the Name field, type `Login.aspx` and then click **OK**.

Configure a White Label Directory in IIS

If you are using a BIC version that contains a white label (WL) directory inside the Components\Cedar directory, create a WL virtual directory in IIS. Complete the following steps.

1. In the **Internet Information Services (IIS) Manager** window, in the left pane, open the tree view until **Web Verifier** displays.
2. Right-click **Web Verifier**, then click **Add Virtual Directory**.
3. In the **Add Virtual Directory** dialog box, complete the following substeps.
 1. In the **Alias** field, type `WL` as the name for the virtual directory.
 2. In the **Physical path** field, type or browse to the **[Installation path]\Brainware Intelligent Capture\Components\Cedar\WL** directory and then click **OK**.

Configure Web Verifier

To configure Web Verifier, complete the following tasks.

1. [Modify the instanceName Value When Using Multiple Web Servers.](#)

2. [Modify the Database Connection Strings for Web Verifier.](#)
3. To enhance application performance, you can optionally enable HTTP compression. For more information, refer to Microsoft Technet.

Modify the *instanceName* Value When Using Multiple Web Servers

To ensure that the *instanceName* value in the *Web.config* is unique across all web servers accessing the same BIC database, complete the following steps.

1. From the *[Installation path]\Brainware Intelligent Capture Web Server* directory, open **Web.config** in a text editor.
2. Search for the following lines.

```
<system.controllers>
<client instanceName="Web Verifier"
remoteObjectRenewalTimeout="180"></client>
```

3. Change *instanceName="Web Verifier"* to *instanceName="Web Verifier [xx]"* with *xx* being unique across the system.

Example *instanceName="Web Verifier 01"* for the first server.

Example *instanceName="Web Verifier 02"* for the second server.

Modify the Database Connection Strings for Web Verifier

To modify the database connection string, complete the following steps.

1. From the *[Installation path]\Brainware Intelligent Capture Web Server* directory, open the **Web.config** file in a text editor.
2. Search for the `<connectionStrings>` element.
3. For a SQL Server database, modify the following values.
 - Set `Data Source` to the required data source.
 - Set `Initial Catalog` to the SQL Server database catalog.
 - Remove `User ID=<UserID>;Password=<UserPassword>;`.
 - Set `Integrated Security` to SSPI.
4. For an ORACLE database, modify the following values.
 - Set `Data Source` to the data source.
 - Set `User ID` to the service account user ID.
 - Set `Password` to the service account password.
5. Save and close the file.
6. Create a copy of the **Web.config** file and move it to *[Installation path]\Brainware Intelligent Capture\bin*.
7. Rename the **Web.config** file copy to **Brainware.System.Project.exe.config**.

Configure Server Security for Web Verifier

To configure server security for Web Verifier, complete the following tasks as necessary.

1. [Add the User Context in SQL Server](#)
2. [Verify the IIS Identity](#)
3. [Set Permissions for BIC Projects](#)
4. [Set Permissions for BIC Bin Directory](#)

Add the User Context in SQL Server

To use Web Verifier, your users need access rights for the SQL Server database with the Web Verifier user context. The default user context is Network Service. You can change the default user context to a service account.

Note: If you log in to SQL Server using Windows authentication, you need to add the domain username to the SQL Server database in addition to the NT Authority/Network Service.

To add the user context to SQL Server, complete the following steps.

1. In **Microsoft SQL Server Management Studio**, in the left pane, click **Security > Logins**.
2. Right-click **Logins** and then click **New Login**.
3. In the **Login** dialog box, click **Search**.
4. In the **Select User or Group** dialog box, in the **Enter the object name to select** field, type either `IIS AppPool\WebVerifierPool` or the name of the user context, click **Check Names** and then click **OK**.
5. In the **Login Properties** dialog box, in the left pane, click **User Mapping**.
6. In the upper right pane, in the **Map** column, select the check box for the required database.
7. In the lower right pane, select the following database roles and then click **OK**.
 - db_datareader
 - db_datawriter
 - db_runner

Verify the IIS Identity

To verify that IIS run under the appropriate identity, complete the following steps.

1. In **Internet Information Services (IIS) Manager**, in the **Connections** pane, open the server node and then click **Application Pools**.
2. In the **Application Pools** pane, right-click **WebVerifierPool** and then click **Advanced Settings**.
3. In the **Advanced Settings** dialog box, under **Process Model**, verify that the **Identity** property has the value `ApplicationPoolIdentity` or the name of the service account.

Set Permissions for BIC Projects

BIC stores all projects in a file system directory. To enable Web Verifier to load projects, you must assign appropriate permissions for the project directory.

To grant permission to the project directory, complete the following steps.

1. In **Windows Explorer**, right-click your projects directory and then click **Properties**.
2. In the **Properties** dialog box, on the **Security** tab, click **Edit**.
3. In the **Permissions** dialog box, click **Add**.
4. In the **Select Users, Computers, Service Accounts, or Groups** dialog box, in the **Enter the object names to select** field, type either `IIS AppPool\WebVerifierPool` or the name of the user context, click **Check Names** and then click **OK**.

Set Permissions for BIC Bin Directory

The Web Verifier application pool or the service account, if used, needs access to the Web Verifier installation directory.

To grant permission to the installation directory, complete the following steps.

1. In **Windows Explorer**, right-click the `[Installation path]\Brainware Intelligent Capture Web Server` directory and then click **Properties**.
2. In the **Properties** dialog box, on the **Security** tab, click **Edit**.
3. In the **Permissions** dialog box, click **Add**.
4. In the **Select Users, Computers, Service Accounts, or Groups** dialog box, in the **Enter the object names to select** field, type either `IIS AppPool\WebVerifierPool` or the name of the user context, click **Check Names** and then click **OK**.
5. Repeat the previous steps for the `[Installation path]\Brainware Intelligent Capture\bin\LogRoot` directory.

Configure Internet Explorer for Web Verifier

To configure Internet Explorer for Web Verifier, complete the following steps.

1. In **Internet Explorer**, click **Tools > Internet Options**.
2. In **Internet Options** dialog box, on the **Security** tab, click **Custom level**.
3. In the **Security Settings** dialog box, under **ActiveX controls and plug-ins**, enable the following settings.
 - Binary and script behaviors
 - Run ActiveX controls and plug-ins
4. Under **Scripting**, enable the following settings.
 - Active scripting
 - Allow status bar updates via script

Note: This setting allows Web Verifier to display information on batches, documents, current

filters, and page numbers in the Internet Explorer status bar.

Implement Single Sign-On Authentication

To enable single sign-on authentication, complete the following tasks as necessary.

1. [Enable the Single Sign-On Authentication.](#)
2. [Modify the Web Verifier Session Timeout.](#)

About the Single Sign-On Authentication for Web Verifier

Web Verifier supports single sign-on (SSO) user authentication. SSO intercepts the login request and either gathers the user credentials, or accepts the user as already authenticated.

BIC provides the SSO functionality as a generic solution. It works with any SSO implementation and configuration that provides the user credential information through an HTTP header. SSO support was tested using Shibboleth 2.x which builds on SAML 2.0 standards.

For information on configuring the SSO service provider, refer to your provider's product documentation.

Enable the Single Sign-On Authentication

To enable single sign-on authentication, complete the following steps.

1. From the *[Installation path]\Brainware Intelligent Capture Web Server* directory, open **Web.config** in a text editor.
2. Search for the `<httpHeaderBasedSso>` element and complete the following substeps.
 1. Set the `enabled` attribute to `true`.
 2. Set the `loginHeader` attribute to the HTTP header attribute name that the SSO service returns.
 3. Set the `sessionHeader` attribute to the default session-ID header that the SSO service returns.

Example

```
<httpHeaderBasedSso loginHeader="remoteuser" enabled="true"  
sessionHeader="ShibSessionID" />
```

3. Save and close the file.

About the Single Sign-On Session and the Web Verifier Session

Using SSO involves two different sessions: the SSO session and the Web Verifier session.

To prevent verifier data loss, the SSO session should have a longer timeout than the Web Verifier session.

The SSO and Web Verifier sessions renew with every server request, such as field validation or opening a batch. The sessions do not renew with client-side actions, such as zooming in on an image or typing a value into a form field without validating it.

For details on how to configure the SSO session timeout, refer to your SSO provider documentation.

Modify the Web Verifier Session Timeout

To modify the Web Verifier session timeout, complete the following steps.

1. From the *[Installation path]\Brainware Intelligent Capture Web Server* directory, open the **Web.config** file in a text editor.
2. Search for the `<sessionState>` element.
3. Set the `timeout` attribute, in minutes, according to your needs.

Configure Windows Authentication

To configure Windows authentication, complete the following tasks as necessary.

1. [Configure Windows Authentication in IIS 7.5 and Higher](#) .
2. [Create a Windows Authentication Version of the Web.config File](#) .
3. [Switch Back to Forms Authentication](#).

About Windows Authentication for Web Verifier

Web Verifier allows you to log in using Windows authentication instead of Forms authentication.

After you configure this option, your users will only be able to log in with Windows authentication.

However, you can use the re-login menu option to login with an account other than your Windows user account, for example as an administrator, to perform certain administrative tasks.

Configure Windows Authentication in IIS 7.5 and Higher

To configure Windows authentication for the Web Verifier in IIS 7.5 and higher, complete the following steps.

Prerequisite

Add the Windows user to the BIC database.

1. In the **Internet Information Services (IIS) Manager** window, in the left pane, open the tree view until **Web Verifier** displays.
2. Click **Web Verifier** and then, in the middle pane, under **IIS**, double-click **Authentication**.
3. In the **Authentication** pane, enable **Windows Authentication** and disable all other authentication methods.
4. Restart any open browser sessions.

Create a Windows Authentication Version of the Web.config File

We recommend maintaining two versions of the Web.config file to simplify switching between the default Forms authentication and Windows authentication methods.

To create a copy of the default Web.config file and modify it for Windows authentication, complete the following steps.

1. From the *[Installation path]\Brainware Intelligent Capture Web Server* directory, create a backup of the **Web.config** file for the Forms authentication method.

Note: You can store this backup Web.config for Forms authentication in any directory.

2. Open the original **Web.config** file in a text editor.
3. Complete the following substeps.
 1. Search for the following line.
`<authentication mode="Forms">`
 2. Replace `Forms` with `Windows`.
`<authentication mode="Windows">`
 3. Remove the following line.
`<forms loginUrl="Login.aspx" defaultUrl="BatchView.aspx" />`
 4. Under the `<authorization>` node, replace the `<deny users="?" />` element with an `<allow users="?" />` element.
 5. Under the `<pages>` node, add an `<pages enableSessionState="true">` element.
 6. Remove all `<location path=>` nodes.
 7. Save and close the file.

Switch Back to Forms Authentication

To switch from Windows authentication mode back to default Forms authentication, complete the following steps.

1. Open **Administrative Tools** and then double-click **Internet Information Services (IIS) Manager**.
2. In the **Internet Information Services (IIS) Manager** window, in the left pane, open the tree view until **Web Verifier** displays.
3. Click **WebVerifier** and then, in the middle pane, under **IIS**, double-click **Authentication**.
4. In the **Authentication** pane, disable **Windows Authentication** and enable **Anonymous Authentication** and **Forms Authentication**.
5. Copy the backed up **Web.config** file to the `[Installation path]\Brainware Intelligent Capture Web Server` directory.
6. Restart any open browser sessions.

Configure Cookies for Web Verifier

To ensure that the browser sends cookies over a secure https network only, complete the following steps.

Prerequisite

Configure SSL on the server.

1. From the `[Installation path]\Brainware Intelligent Capture Web Server` directory, open the **Web.config** file in a text editor.
2. In the `<configuration>` element, search for the following line.
`<system.web>`
3. Under `<system.web>`, add the following line.
`<httpCookies requireSSL="true" />`
4. To apply forms authentication, search for the following line.
`<forms loginUrl="Login.aspx" defaultUrl="BatchView.aspx" />`
5. Add the `requireSSL` attribute.

```
<forms loginUrl="Login.aspx" defaultUrl="BatchView.aspx"
requireSSL="true" />
```

6. Save and close the file.
7. Optional. To prevent other applications from accessing Web Verifier cookies, deploy Web Verifier in one of the following ways.
 - As the root level website.
 - As the only web application under a website in IIS.

About Web Verifier Performance

Consider the following information to improve Web Verifier performance.

Image Conversion

Opening documents in Web Verifier that failed during classification or extraction may cause performance issues. The Runtime Server properties provide the following settings to convert failed images to PNG to speed up the loading time.

- Convert image to display format after failed classification
- Convert image to display format after failed extraction

For more information, see "About display formats" and "Set display format" in the *Brainware Intelligent Capture Runtime Server Help*.

Remote Matching Service

The Remote Matching Service (RMS) is an implementation of the Associative Search Engine. RMS is capable of supporting large search data pools and is highly recommended for BIC installations including Web Verifier.

For more information, see "Associative Search Engine" in the *Brainware Intelligent Capture Designer Help*.

Delayed Validation

The "Allow delayed validation" feature increases the validation performance in Verifier and Web Verifier by reducing the number of server requests.

For more information, see "About delayed validation" and "Modify the validation rules for a field" in the *Brainware Intelligent Capture Designer Help*.

Use Traditional Chinese

If you choose Chinese as UI language, Web Verifier uses Simplified Chinese by default.

To change to Traditional Chinese, complete the following steps.

1. From the *[Installation path]\Brainware Intelligent Capture Web Server\bin\Resources* directory, create a backup copy of the **zho** directory.
2. Copy all files from the *[Installation path]\Brainware Intelligent Capture Web Server\bin\Resources\cmn* directory to the *[Installation path]\Brainware Intelligent Capture Web Server\bin\Resources\zho* directory.

3. From the *[Installation path]\Brainware Intelligent Capture Web Server* directory, open the **Web.config** file in a text editor.
4. Search for the following line.


```
<add key="LanguageDisplayName_ZHO" value="中文简体" />
```
5. Modify the line as follows.


```
<add key="LanguageDisplayName_CMN" value="中文繁體" />
```
6. Save and close the file.
7. Restart any open browser sessions.

Access Web Verifier

To access Web Verifier, complete the following step.

- In your browser, type `http://localhost/WebVerifier/login.aspx`.

Additional Columns in Verifier or Web Verifier

You can display additional columns in Verifier and Web Verifier. If you display the external group ID column, verify that the group ID matches the group ID you created for the users.

You can add the following columns to batch view.

- ExternalGroupId
- ExternalBatchId
- TransactionId
- TransactionType

Display and Name Additional Verifier Columns: SQL Server

To display additional Verifier columns from a SQL database, in Microsoft SQL Server Management Studio, in your BIC database, modify and execute any of the following commands.

- External group ID

```
exec sp_SetGlobalApplicationSetting
'SysAppBatchColumnExternalGroupId', '[Column header name, for example
User Group]', True
```

- External batch ID

```
exec sp_SetGlobalApplicationSetting
'SysAppBatchColumnExternalBatchId', '[Column header name, for example
Batch Group]', True
```

- Transaction ID

```
exec sp_SetGlobalApplicationSetting 'SysAppBatchColumnTransactionId',
'[Column header name, for example Transaction]', True
```

- Transaction type

```
exec sp_SetGlobalApplicationSetting
'SysAppBatchColumnTransactionType', '[Column header name, for example
Transaction Type]', True
```

Display and Name Additional Verifier Columns: Oracle

To display additional Verifier columns from an Oracle database, from the SQL*Plus or ORACLE Management Console, in your BIC database, execute any of the following commands.

- External group ID

```
exec sp_SetGlobalApplicationSetting
('SysAppBatchColumnExternalGroupId', '[Column header name, for
example User Group]', 1)
```

- External batch ID

```
exec sp_SetGlobalApplicationSetting
('SysAppBatchColumnExternalBatchId', '[Column header name, for
example Batch Group]', 1)
```

- Transaction ID

```
exec sp_SetGlobalApplicationSetting
('SysAppBatchColumnTransactionId', '[Column header name, for example
Transaction]', 1)
```

- Transaction type

```
exec sp_SetGlobalApplicationSetting
('SysAppBatchColumnTransactionType', '[Column header name, for
example Transaction Type]', 1)
```

Display Additional Web Verifier Columns

The PostImportBatch event in the project script displays additional Web Verifier columns.

For more information on the event, see “PostImportBatch” in the *Brainware Intelligent Capture Scripting Help*.

To display additional columns in Web Verifier, complete the following steps.

1. From the *[Installation path]\Brainware Intelligent Capture Web Server* directory, open the **Web.config** file in a text editor.
2. Search for the following elements and set the `visible` attribute to `true` for the columns you want to display.
 - `externalGroupIdColumn`
 - `externalBatchNameColumn`
 - `transactionIdColumn`
 - `transactionTypeColumn`

3. Save and close the file.
4. Restart any open browser sessions.

Change the Web Verifier Column Names

To change the display names for any additional columns in Web Verifier, complete the following steps.

1. From the *[Installation path]\Brainware Intelligent Capture Web Server\bin\resources\[language code]* directory, open the **Brainware.Verifier.WebClient.resx** file in a text editor.
2. Search for the following `<data name=>` elements.
 - TEXT_EXTERNALBATCH_NAME
 - TEXT_EXTERNAL_GROUP_ID
 - TEXT_TRANSACTION_ID
 - TEXT_TRANSACTION_TYPE
3. Set the `<value>` attributes with the names you want to display.
4. Save and close the file.
5. Restart any open browser sessions.

Configure Global Application Settings

To configure global application settings, complete the following tasks as necessary.

1. Optional. Configure workflow history reporting for [SQL Server](#) or [Oracle](#).
2. Optional. Disable batch deletion for [SQL Server](#) or [Oracle](#).
3. Optional. Modify the URL expiration time for [SQL Server](#) or [Oracle](#).

About Workflow History Reporting

You can activate the workflow history reporting for documents, fields, table cells, classification, learning, and OCR and document separation. Changing these settings takes immediate effect and applies to all users.

Configure Workflow History Reporting: SQL Server

To configure workflow history reporting for SQL Server, in Microsoft SQL Server Management Studio, in your BIC database, execute any of the following commands.

- For documents

```
exec sp_SetGlobalApplicationSetting
'SysAppHistoryReportingActivatedForDocument', 'True', True
```

- For fields

```
exec sp_SetGlobalApplicationSetting
'SysAppHistoryReportingActivatedForField', 'True', True
```

- For fields and table cells

```
exec sp_SetGlobalApplicationSetting  
'SysAppHistoryReportingActivatedForTableCell', 'True', True
```

- For classification

```
exec sp_SetGlobalApplicationSetting  
'SysAppHistoryReportingActivatedForClass', 'True', True
```

- For OCR and document separation

```
exec sp_SetGlobalApplicationSetting  
'SysAppHistoryReportingActivatedForPage', 'True', True
```

- For learning

```
exec sp_SetGlobalApplicationSetting  
'SysAppHistoryReportingActivatedForLearning', 'True', True
```

Configure Workflow History Reporting: Oracle

To configure workflow history reporting for Oracle, in SQL*Plus or Oracle Management Console, in your BIC database, execute any of the following commands.

- For documents

```
exec sp_SetGlobalApplicationSetting  
( 'SysAppHistoryReportingActivatedForDocument', 'True', 1)
```

- For fields

```
exec sp_SetGlobalApplicationSetting  
( 'SysAppHistoryReportingActivatedForField', 'True', 1)
```

- For fields and table cells

```
exec sp_SetGlobalApplicationSetting  
( 'SysAppHistoryReportingActivatedForTableCell', 'True', 1)
```

- For classification

```
exec sp_SetGlobalApplicationSetting  
( 'SysAppHistoryReportingActivatedForClass', 'True', 1)
```

- For OCR and document separation

```
exec sp_SetGlobalApplicationSetting  
( 'SysAppHistoryReportingActivatedForPage', 'True', 1)
```

- For learning

```
exec sp_SetGlobalApplicationSetting  
( 'SysAppHistoryReportingActivatedForLearning', 'True', 1)
```

About Disabling Batch Deletion in Runtime Server and Designer

You can disable batch deletion in Runtime Server and Designer. Changing these settings takes immediate effect and applies to all users.

Disable Batch Deletion: SQL Server

To disable batch deletion for SQL Server, in Microsoft SQL Server Management Studio, in your BIC database, execute any of the following commands.

- For Designer

```
exec sp_SetGlobalApplicationSetting  
'SysAppBatchDeletionDisabledInDesigner', 'True', True
```

- For Runtime Server

```
exec sp_SetGlobalApplicationSetting  
'SysAppBatchDeletionDisabledInRTS', 'True', True
```

Disable Batch Deletion: Oracle

To disable batch deletion for Oracle, in SQL*Plus or Oracle Management Console, in your BIC database, execute any of the following commands.

- For Designer

```
exec sp_SetGlobalApplicationSetting  
( 'SysAppBatchDeletionDisabledInDesigner', 'True', 1)
```

- For Runtime Server

```
exec sp_SetGlobalApplicationSetting  
( 'SysAppBatchDeletionDisabledInRTS', 'True', 1)
```

About Modifying the URL Expiration Time for Web Verifier

You can modify the URL expiration time for Web Verifier. Changing these settings takes immediate effect and applies to all users.

Modify the URL Expiration Time: SQL Server

To modify the URL expiration time for SQL Server, in Microsoft SQL Server Management Studio, in your BIC database, complete the following step.

- Execute the following command, specifying the expiration time in seconds for the second parameter.

```
exec sp_SetGlobalApplicationSetting  
'SysAppUrlSignatureExpirationPeriod', '300', True
```

Modify the URL Expiration Time: Oracle

To modify the URL expiration time for Oracle, in SQL*Plus or Oracle Management Console, in your BIC database, complete the following step.

- Execute the following command, specifying the expiration time in seconds for the second parameter.

```
exec sp_SetGlobalApplicationSetting
('SysAppUrlSignatureExpirationPeriod', '300', 1)
```

Configure BIC Security

To configure BIC security, review the following topics and complete the tasks as necessary.

1. [File System Security](#)
2. [Recommended Accounts and Groups](#)
3. [Configure Access to Project Data](#)
4. [About the Service Account on a Domain Network](#)
5. [About the Service Account for System Monitoring](#)
6. [About the Service Account for Email Importing](#)
7. [About INI File Encryption](#)
8. [Encrypt a Password for a Database Connection String](#)
9. [About User Password Encryption](#)
10. [Change the Hashing Algorithm](#)

File System Security

Although BIC provides application-level security, the BIC applications rely on the integrated Windows file system security to control access to application and project data in SDP, DAT, and WDC files.

BIC uses a combination of shared and file and directory permissions to control the access of users, groups, and applications to directories and files.

The following table lists the available file permissions.

File Permission	Access Granted
Read	Allows the user or group to read the file and view its attributes, ownership, and permissions.
Write	Allows the user or group to overwrite the file, change its attributes, and view its ownership and its permissions.
Read and	Allows the user or group to execute the file.

File Permission	Access Granted
Execute	Includes the Read permissions.
Modify (CHANGE)	Allows the user or group to modify and delete the file. Includes the Read, Write, and Read and Execute permissions.
Full Control	Allows the user or group to change the files permissions and to take ownership of the file. Includes all other file permissions.

The following table lists the available directory permissions.

Directory Permission	Access Granted
Read	Allows the user or group to view the files, folders, and subfolders of the parent folder and to view the folder attributes, ownership, and permissions.
Write	Allows the user or group to create new files and folders within the parent folder, view folder ownership and permissions, and change folder attributes.
List Folder Content	Allows the user or group to view the files and subfolders in the folder.
Read and Execute	Allows the user or group to navigate through all files and subfolders. Includes the Read and List Folder Contents permissions.
Modify (CHANGE)	Allows the user to delete the folder. Includes the Write and Read and Execute permissions.
Full Control	Allows the user or group to change the folder permissions and to take ownership of the folder. Includes all other folder permissions.

Recommended Accounts and Groups

To control access to BIC project data, we recommend a combination of Discretionary Access Control (DAC) and Role-based Access Control (RBAC).

The DAC model allows the system administrators to control which users can access objects and resources and the operations they can perform.

The RBAC model, also known as non-discretionary model, grants access based on the rights and permissions of roles and groups. The users inherit their rights and permissions from their assigned roles and groups.

The following table lists the groups and accounts recommended for each BIC implementation.

Group / Account Name	Purpose
BIC Project Users	Global group containing all users designated as BIC project designer or data verifier. Add this group to the BIC Users group.
BIC Admin	Global group containing all users designated as a BIC system administrator. Add this group to the BIC group on all RTS servers and RTS remote administration workstations.
BIC	Local group used to grant access to local BIC resources. Create this group on all RTS server and RTS remote administration workstations.
BIC Users	Local group used to grant access to the project directory. Create this group on the BIC server on which the project directory resides.
BIC RTSvc	Service account used to start the BIC service manager. Add this user to the BIC Admin group and the local administrators group on all BIC servers and remote administration workstations.

The following table lists the groups and accounts, assigned permissions, and the directories and objects on which you need to apply the permissions for each BIC implementation.

Group / Account Name	Permission Type: Shared	Permission Type: NTFS	Directory/Objects Assigned On
Brainware Intelligent Capture	Full Control	Full Control	C:\Program Files\[company]\[ProjectName]
Brainware Intelligent Capture Users	Change	Modify	C:\Program Files\[company]\[ProjectName]

Configure Access to Project Data

BIC uses a hierarchical file structure to store project-related data, where the project directory is at the highest level.

All BIC components including services, applications, license engines, and users need appropriate access rights to the project directory and its subfolders.

To configure the access rights to the BIC project directory, complete the following steps.

1. In **Windows Explorer**, right-click your projects directory and then click **Properties**.
2. In the **Properties** dialog box, on the **Sharing** tab, click **Advanced Sharing**.
3. In the **Advanced Sharing** dialog box, select **Share this folder**.
4. In the **Share name** box, type a name for the share and then click **Permissions**.
5. In the **Permissions for Projects** dialog box, complete the following substeps.
 1. Click **Add**.
 2. In the **Select Users, computers, Service Accounts or Groups** dialog box, in the **Enter the object names to select** field, type the local BIC group name and click **OK**.
 3. Repeat the previous steps to add the local administrators and BIC users group names.
 4. For the local BIC group and the local administrators group, select **Full Control**.
 5. For the local BIC users group, select **Change**.
 6. Select the **Everyone** group, click **Remove** and then click **OK**.
6. In the **Properties** dialog box, on the **Security** tab, complete the following substeps.
 1. Add the local BIC group and the local administrators group with **Full Control** permission.
 2. Add the local BIC users group with **Change** permission.
 3. Select the **Everyone** group, click **Remove** and then click **OK**.

About the Service Account on a Domain Network

The Runtime Server service utilizes a Windows service to manage the Runtime Server instances and the document processing.

When running BIC on multiple servers located on a domain network, we recommend assigning a domain user to the Runtime Server service against the Windows service. This allows BIC to communicate with all servers running the service across the domain.

The service account, used in BIC, needs permissions for any file or directory shares across the servers to allow the Runtime Server service to access all project-related files.

Note: Do not use the service account to log into the system, either locally or through Remote Desktop. You can configure the Security Settings for the “Deny log on locally” and “Deny log on through Remote Desktop Services” policies in Windows on the system running the services.

About the Service Account for System Monitoring

You can use the System Monitoring service to send emails to selected users for any Runtime Server errors or warnings.

The service user account used for System Monitoring needs sufficient rights on the server and domain to send emails.

About the Service Account for Email Importing

BIC provides the ability to import emails, automatically download emails from a mailbox, and import the emails into the BIC system. The Runtime Server service needs sufficient access rights to access the mailbox and to download emails.

About INI File Encryption

BIC allows password encryption in INI files for database and SAP connection strings by using RSA encryption. RSA encryption requires a public and a private key.

For more information, see "Password encryption for database connection strings" in the *Brainware Intelligent Capture Scripting Help*.

Encrypt a Password for a Database Connection String

Password encryption in CONFIG files is optional, but highly recommended. To provide an encrypted password for the database connection in a configuration file, complete the following steps.

1. In the **[*Installation path*]\Brainware Intelligent Capture\bin** directory, create a new batch file and give it a meaningful name, such as **CreateEncryptedPassword.bat**.
2. Copy one of the following options to the batch file, replacing `MyPassword` with the password you want to encrypt.

Note:

The maximum character length for a password to encrypt using **RSA-1024** is 30.

The maximum character length for a password to encrypt using **RSA-3072** is 280.

- To encrypt the password using the internal RSA-3072 key, use the following option.

```
DstCrypt.exe /text "MyPassword" >> EncryptedPW_
InternalKeys3072.txt
```

- To encrypt the password using the internal RSA-1024 key, use the following option.

```
DstCrypt.exe /text "MyPassword" /keysize "1024" >> EncryptedPW_
InternalKeys1024.txt
```

3. Save and close the file.
4. In **Windows Explorer**, double-click the batch file.
5. From **[*Installation path*]\Brainware Intelligent Capture\bin**, open **EncryptedPassword.txt** in a text editor and copy the encrypted password to the clipboard.

6. Open the required configuration file in a text editor.
7. Search for the `<connectionStrings>` element.
8. In the `<add name>` element, set password as an asterisk.

Example

```
<add name="Entities" Password=*>
```

9. In the `<appSettings>` element, add a line with your encrypted password according to the following example.

Example

```
<appSettings>
<add key="EncrPwd" value="The_encrypted_Password"/>
</appSettings>
```

10. Save and close the file.

About User Password Encryption

For security reasons and to ensure unfeasibility of password decryption, user passwords are encrypted using a one-way hashing algorithm.

BIC stores only the hash values in the database to authenticate the user.

The following hashing algorithms are available.

- SHA-256 (default value)
- SHA-512

Note:

If the hashing algorithm is changed, the system updates the database with the recalculated hash value as soon as the user logs in to a BIC application.

Change the Hashing Algorithm

To change the hashing algorithm, complete one of the following steps.

Note:

For more information about the possible hashing algorithms, see [About User Password Encryption](#).

- For a **SQL Server** database, in **Microsoft SQL Server Management Studio**, in your BIC database, update the following command with the desired hashing algorithm and then execute the command.

```
exec sp_SetGlobalApplicationSetting 'SysAppHashingAlgorithm', '  
[hashing algorithm]', True
```

Example

```
exec sp_SetGlobalApplicationSetting 'SysAppHashingAlgorithm', 'SHA-512', True
```

- For an **Oracle** database, from the **SQL*Plus or ORACLE Management Console**, in your BIC database, update the following command with the desired hashing algorithm and then execute the command.

```
exec sp_SetGlobalApplicationSetting ('SysAppHashingAlgorithm', '[hashing algorithm]', 1)
```

Example

```
exec sp_SetGlobalApplicationSetting ('SysAppHashingAlgorithm', 'SHA-512', 1)
```

Configure BIC Runtime Components

To configure BIC runtime components, review the following topics and complete the tasks as necessary.

1. [About RTS Remote Administration MMC](#)
2. [Configure the Runtime Service Manager Service](#)
3. [Configure the RTS Remote Administration MMC Snap-In](#)
4. [Configure the Email Import Feature in Microsoft Outlook](#)

About RTS Remote Administration MMC

Before you can use BIC, you must configure the Runtime Service Manager (RTS).

The RTS Remote Administration Microsoft Management Console (MMC) snap-in enables you to start and stop multiple Runtime Servers remotely from a single workstation on the network. The BIC installation creates a default console, called Runtime Server Administration that you can use to configure the RTS Remote Administration MMC snap-in.

Configure the Runtime Service Manager Service

To configure the Runtime Service Manager service, complete the following steps.

Prerequisite

Verify that the BIC RTSSvc domain user exists.

1. Log in to **Windows** using an account with administrator rights.
2. In **Windows Services**, right-click the **Brainware Intelligent Capture Runtime Service Manager** service and then click **Properties**.
3. In the **Brainware Intelligent Capture Service Manager Properties** dialog box, on the **General** tab, set the **Startup type** according to your needs.
4. On the **Log On** tab, select **This account** and then click **Browse**.
5. In the **Select User** dialog box, click **Locations**.
6. In the **Locations** dialog box, select the domain that has the required account and then click **OK**.

7. In the **Select User** dialog box, in the **Enter the object name to select** box, type the domain user name, such as `BIC RTSSVC`, click **Check Names**, and then click **OK**.
8. Type the password for the user in the **Password** and the **Confirm password** fields and then click **OK**.

Configure the RTS Remote Administration MMC Snap-In

To configure the snap-in, complete the following steps.

1. Verify that the **Brainware Intelligent Capture Runtime Service Manager** service is running. This lets you connect by MMC to the machine.
2. Identify one free configurable port available in any TCP/IP network or the Internet across firewalls.

Note: The default port number is 50607.

3. Verify one of the following prerequisites.
 - The administration workstation resides on the same LAN segment as the RTS services.
 - In a sub-netted network, a name resolution system is in place to allow clients on one subnet to locate resources on another subnet.
4. Start **Brainware Intelligent Capture Runtime Service**.
5. In the **Runtime Server Administration** window, in the left pane, right-click **Runtime Server Administration** and click **New RTS Group**.
6. In the **New Group** dialog box, type a group name and click **OK**.
7. Open the **Runtime Server Administration** node, right-click the newly created group, and then click **New Machine**.
8. In the **Group Management** dialog box, complete the following substeps.
 1. From the **Domains** list, select the required domain and then click **Search**.
 2. In the left pane, select the required machines, click **>>** and then click **OK**.
9. In the **Runtime Server Administration** window, complete the following substeps.
 1. In the left pane, right-click the newly added machine and then click **License**.
 2. In the **License Information** dialog box, verify or change the license path and then click **OK**.
 3. In the left pane, right-click the newly added machine and then click **New > RTS Instance**.
 4. In the **New RTS Instance** dialog box, type an instance name and then click **OK**.

Configure the Email Import Feature in Microsoft Outlook

You can optionally configure BIC to import emails from Microsoft Outlook. To configure the email import feature, complete the following steps.

1. In **Windows Control Panel**, click **Mail**.
2. In the **Mail** dialog box, click **Add**.
3. In the **New Profile** dialog box, type `RTS_Import` and then click **OK**.

4. In the **Add New Account** dialog box, select **Manually configure server settings or additional server types** and then click **Next**.
5. In the **Choose Service** page, select **Microsoft Exchange or compatible service**.
6. In the **Server Settings** page, complete the following substeps.
 1. In the **Server** field, type the name of your Microsoft Exchange Server.
 2. Clear the **Use Cached Exchange Mode** check box.
 3. In the **User Name** field, type the user name and then click **Next**.
7. To create the account and close the wizard, click **Finish**.
8. In the `[[Installation path]\Brainware Intelligent Capture` directory, create a new batch file that contains the following line and then run the file.

```
DstHost.exe /TestMailUI
```

9. In the **Outlook login** dialog box, complete the following substeps.
 1. In the **User name** field, type `[domain name]\[user name]` and in the **Password** field, type the password.
 2. Select **Remember my credentials** and then click **OK**.
10. From the Brainware Intelligent Capture log directory, open the latest `I_[YYYYMMDD]_DistillerRuntimeServiceHost_[PID].log` file and check for a success or error message, such as `Managed to open the folder 'Inbox'`.
11. In the `[[Installation path]\Brainware Intelligent Capture` directory, create a new batch file that contains the following line and then run the file.

```
DstHost.exe /TestMail
```

Note: This writes a message to the log file, but does not open the **Outlook login** dialog box.

About the Desktop Heap Size

If you run more than 10 concurrent Web Verifier sessions or Runtime Service instances, modify the Windows desktop heap size to prevent internal memory issues.

Modify the Desktop Heap Size

To modify the desktop heap size, complete the following steps.

1. Start Windows Registry Editor and back up the registry settings.
2. Navigate to `HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Control\Session Manager\SubSystems`.
3. In the right pane, right-click the **Windows** entry, and then click **Modify**.
4. In the **Edit String** dialog box, in the editing field, modify the third argument of the **SharedSection** parameter, which defines the desktop heap size.

Note: For information about the appropriate heap size, see [Ideal Desktop Heap Size](#).

5. Reboot the server.

Ideal Desktop Heap Size

Determine the ideal desktop heap size with the following table.

Number of concurrent Web Verifier or Runtime Server instances	Desktop heap size in KB
1 - 10	Operating system default value
11 - 24	1024
25 - 36	1536
37 - 48	2048
49 - 60	2560
61 - 72	3072

About Logging

BIC creates new log files daily in the log directory.

You can configure the [logging level](#), [location](#), and [retention time](#) for your application log files.

The default log directory is *[Installation path]\Brainware Intelligent Capture\bin\LogRoot\Log*.

Notes

- Application users must have permission to write to the log directory.
- When the database or the specified `LogOutDir` is inaccessible or no `LogOutDir` is defined, logging automatically redirects to the default log directory.
- If the default log directory is inaccessible, the application redefines the default log directory as the first writable location listed.
 1. `%TMP%\DstLog`
 2. `%TEMP%\DstLog`
 3. `%USERPROFILE%\DstLog`
 4. `%WINDIR%\Temp\DstLog`
- If an application is unable to write to the log file, a warning appears in the system logs.

Log Files

Each application log file contains the following information.

Entry Nr.	Description
1	Type of message such as Info, Warning, or Error
2	Severity of message
3	Time logged
4	Process ID (PID)
5	Overall used / available physical memory in KB
6	Overall used / available virtual memory in KB
7	Used physical / virtual memory by this RTS instance in KB
8	Number of process handles used by this RTS instance
9	GDI resources / UserObjects used by this RTS instance
10	Message text

The following log files are available in the log directory.

Application log file	Description
V_*.log	Verifier messages including custom script errors.
VA_*.log	Advanced Verifier messages.
VL*.log	Local Verifier messages.
H_*.log	Runtime Server Host (DstHost) messages for a single RTS instance. Note: The standard Runtime Server log files include system level resource information and, in case of a system failure, special error logs.
L_*.log	Learnset Manager messages, such as when the user triggers document learning, or backs up the learnset.

Application log file	Description
D_*.log	Designer messages including script errors.
U_*.log	Web Verifier and external application messages.
S_*.log	Service Manager (DstMgr) messages, such as start and end of service, restart, or failures.
M_*.log	System Monitoring (DstEvent) messages. Holds all system messages and can log error messages across all server machines and hosts.

Component log file	Description
I_*.log	Component log files for all applications.

Error log file	Description
C_*.log	In the event of system or application failures, BIC creates an additional error log file named C_<Process ID>_yyyymmdd.log .

Logging Levels

The following application logging levels are available.

Logging level	Description
0	No logging.
1	Log only errors.
2	Log errors and warnings.
3	Log errors, warnings, and information.

Configure the Logging Level

To configure the logging level, complete the following step in your BIC database.

Note: The specified `LogTraceLevel` does not apply to Runtime Server instances. For more information about setting the logging level for an RTS instance, see "Define logging levels" in the *Brainware Intelligent Capture Runtime Server Help*.

- Update the following command with the desired [logging level](#) and then execute the command.

- **For SQL Server**

```
exec sp_SetGlobalApplicationSetting 'LogTraceLevel', '[logging level]', True
```

Example

```
exec sp_SetGlobalApplicationSetting 'LogTraceLevel', '1', True
```

- **For Oracle**

```
exec sp_SetGlobalApplicationSetting ('LogTraceLevel', '[logging level]', 1)
```

Example

```
exec sp_SetGlobalApplicationSetting ('LogTraceLevel', '1', 1)
```

Configure the Location of the Application Log Files

To configure the location of the application log files, complete the following step in your BIC database.

Notes

- Update the following command with the desired log file directory and then execute the command.

Note: To revert to the default setting, set `LogOutDir` to an empty string.

- **For SQL Server**

```
exec sp_SetGlobalApplicationSetting 'LogOutDir', '[log file directory]', True
```

Example

```
exec sp_SetGlobalApplicationSetting 'LogOutDir', 'C:\Program Files (x86)\Brainware\Log Files', True
```

- **For Oracle**

```
exec sp_SetGlobalApplicationSetting ('LogOutDir', '[log file location]', 1)
```

Example

```
exec sp_SetGlobalApplicationSetting ('LogOutDir', 'C:\Program
Files (x86)\Brainware\Log Files', 1)
```

Configure the Retention Time of Application and Error Log Files

To configure the retention time of application and error log files, complete the following step in your BIC database.

Notes

- The specified `LogTotalDaysToKeepFiles` does not apply to Runtime Server instances. For more information about deleting log files for Runtime Server, see "Delete log files" in the *Brainware Intelligent Capture Runtime Server Help*.
- Each BIC application deletes its own file.
- Cleaning is done once per day.
- To determine whether a file is to be deleted, the cleaning process uses the creation time of the file, which is part of the file name.
- If this setting is not configured, no files are deleted.
- To revert to the default setting, set `LogTotalDaysToKeepFiles` to 0.
- Update the following command with the desired number of days and then execute the command.

- **For SQL Server**

```
exec sp_SetGlobalApplicationSetting 'LogTotalDaysToKeepFiles',
 '[Number of Days]', True
```

Example

```
exec sp_SetGlobalApplicationSetting 'LogTotalDaysToKeepFiles',
 '5', True
```

- **For Oracle**

```
exec sp_SetGlobalApplicationSetting ('LogTotalDaysToKeepFiles',
 '[Number of Days]', 1)
```

Example

```
exec sp_SetGlobalApplicationSetting ('LogTotalDaysToKeepFiles',
 '5', 1)
```

OCR Engine Languages

The following table lists the OCR engine languages supported by FineReader 10 and 11.

Supported OCR languages		
Bulgarian	Italian	Romanian

Supported OCR languages		
Chinese Simplified *	Japanese *	Russian *
Chinese Simplified + English *	Japanese + English *	Slovak
Czech	Korean *	Slovenian
Danish	Korean + English * Note: Only with FineReader 11	Spanish
Digits	KoreanHangul	Swedish
Dutch	Latvian	Thai *
English	Lithuanian	Turkish
Estonian	Norwegian	Ukrainian *
Finnish	NorwegianBokmal	Vietnamese *
French	NorwegianNynorsk	CMC7
German	Polish	E13B
Greek *	Portuguese Brazilian	
Hungarian	Portuguese Standard	

*: These languages require support of double byte and extended ASCII character sets. To avoid performance loss, do not use more than one DBCS language in a project.

Available OCR Engines

The following optional OCR engines are available, but require separate licensing.

Cleq Barcode Engine

Reads handwritten and machine-printed data and bar code information. It reads 18 types of bar codes.

FineReader10 OCR Engine

Supports Chinese, Korean and Japanese characters in addition to English, German, Italian, French, and Spanish characters. Converts paper-based or scanned images to editable text.

FineReader11 OCR Engine

Supports OCR of several additional languages and features several improvements in the OCR output quality relative to FineReader 10.

- Receipt Mode
- Improved auto-orientation
- Improved OCR of amounts with leading or trailing asterisks
- Improved OCR of amounts with leading dollar sign

CloudOCR Engine

The CloudOCR engine uses Microsoft's Computer Vision API to recognize hand written, printed, and mixed English text from documents, zones, and fields.

Prerequisites

- On azure.microsoft.com, create an account and add **Computer Vision**.

This provides you with a subscription key and a base endpoint needed to configure the CloudOCR engine in Designer.

For more information, see "Recognition Techniques and Engines | CloudOCR Engine" in the *Brainware Intelligent Capture Designer Help*.

Kadmos 5 OCR Engine Client Edition

Used for handwriting recognition.

Kadmos 5 OCR Engine Server Edition

A server edition capable of processing for multiple users and on multiple processors is available by additional licensing.

QualitySoft Barcode Engine

Supports both grayscale and color images and recognizes 19 different bar code types.

About Automated Update

You can enable your system to automate updates to your BIC workstations. The automated update feature compares the build level files in the shared network directory and local update directory, and if required, an update performs before the application starts.

If you did not configure the automated update feature during the installation process, you can configure the feature manually.

Note: This feature is not available for all versions of BIC. For details, refer to the appropriate *Brainware Intelligent Capture Release Notes*.

Modify the Batch File

To modify the batch file to automate updates, complete the following steps on each BIC server and workstation.

Prerequisite

Determine a shared network directory on a server to incorporate the update files. All BIC workstations must have access permissions to this directory.

1. From the *[Installation path]\Brainware Intelligent Capture\bin* directory, open the **AutoInstall.bat** file in a text editor.
2. Search for the following line.

```
SET SHAREDNETFOLDER  
=\\YourNetworkInstallServerName\YourInstallShareName
```

3. Modify `\\YourNetworkInstallServerName\YourInstallShareName` to your shared network directory.
4. Save and close the file.

Modify the Application Shortcuts for Verifier and Designer

To set up Designer and Verifier to run the automated update feature each time they start, complete the following steps.

1. In the **Windows** start menu, right-click the **Designer** application and then click **Properties**.
2. On the **Shortcut** tab, in the **Target** field, change **DstDsr.exe** to **DstDsr_AutoUpdate.bat** and then click **OK**.
3. In the **Windows** start menu, right-click the **Verifier** application and then click **Properties**.
4. On the **Shortcut** tab, in the **Target** field, change **DstDsr.exe** to **DstDsr_AutoUpdate.bat** and then click **OK**.

Automate Runtime Server Updates

To configure the automated update for Runtime Server, you can create a Windows task.

In Windows Task Scheduler, create a new task that executes the following steps.

1. To stop the RTS service, in *[Installation path]\Brainware Intelligent Capture\bin* directory, run **Stop RTS running as NT Service.bat**.

Note: Verify that RTS is not actively processing documents before you stop the service.

2. In *[Installation path]\Brainware Intelligent Capture\bin* directory, run **AutoInstall.bat**
3. To start the RTS service, in *[Installation path]\Brainware Intelligent Capture\bin* run **Start RTS running as NT Service.bat**.

About Port Configuration

In case of a conflict in port assignments or for the purpose of firewall configuration, you can change the port the Runtime Server uses for the TCP/IP communication channel.

The Runtime Server service, the instance processes, and the MMC use the same Port registry setting. The default port is 50607.

Configure a Different Port for Runtime Server

To configure a different port for Runtime Server, complete the following steps.

1. In **Windows** registry, complete one of the following substeps.
 - For a 32-bit machine, navigate to `HKEY_LOCAL_MACHINE\SOFTWARE\Hyland_BW\Services`.
 - For a 64-bit machine, navigate to `HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Hyland_BW\Services`.
2. In the right pane, right-click and then click **New > DWORD (32-bit) Value**.
3. In the **Name** field, type `Port`.
4. Right-click the **Port** key and then click **Modify**.
5. In the **Edit DWORD (32-bit) Value** dialog box, in the **Value** data field, type the number of an available port and then click **OK**.
6. Restart **Brainware Intelligent Capture Runtime Server** service.
7. Repeat the previous steps on all BIC servers.

File Permission Matrix

The following tables list the various file permissions used within BIC.

Role/Group	Description
Administrators	Users with full access rights to all application modules and features.
Developers	Users that develop, maintain, and enhance projects.
Learnset Manager	Typically one single user responsible for maintaining the project learnsets.
Advanced Verifiers	Several users responsible for identifying documents for improvements to the project learnset.
Standard Verifiers	Users responsible for document correction.

Role/Group	Description
RTS Service User	The service account responsible for running the service for automatic document processing. Configured only on the server machines.

The following table lists the required NTFS permissions.

Directory	Groups	Full Control	Modify	Read & Execute	List Folder Content	Read	Write	No Access
License Share	Administrators Developers Learnset Manager Advanced Verifiers Standard Verifiers RTS Service User	-	-	x	x	x	x	-
Common Folder	Administrators Developers Learnset Manager Advanced Verifiers	x	x	x	x	x	x	-
	Standard Verifiers RTS Service User	-	-	-	-	-	-	x
Global Project	Administrators	x	x	x	x	x	x	-

Directory	Groups	Full Control	Modify	Read & Execute	List Folder Content	Read	Write	No Access
	Developers Learnset Manager RTS Service User							
	Advanced Verifiers Standard Verifiers	-	-	x	x	x	-	-
Local Project	Administrators Developers	x	x	x	x	x	x	-
	Learnset Manager RTS Service User Standard Verifiers	-	-	-	-	-	-	x
	Advanced Verifiers	x	x	x	x	x	x	-
Local Learnset	Administrators Developers	x	x	x	x	x	x	-
	Learnset Manager RTS Service User Standard Verifiers	-	-	-	-	-	-	x
	Advanced	x	x	x	x	x	x	-

Directory	Groups	Full Control	Modify	Read & Execute	List Folder Content	Read	Write	No Access
	Verifiers							
Global Learnset	Administrators Developers Learnset Manager RTS Service User	x	x	x	x	x	x	-
	Advanced Verifiers Standard Verifiers	-	-	x	x	x	x	-
ASE Pool	Administrators Developers RTS Service User	x	x	x	x	x	x	-
	Learnset Manager Advanced Verifiers Standard Verifiers	-	-	x	x	x	-	-
ASSA CSV File	Administrators Developers RTS Service User	x	x	x	x	x	x	-
	Learnset Manager	-	-	-	-	-	-	x

Directory	Groups	Full Control	Modify	Read & Execute	List Folder Content	Read	Write	No Access
	Advanced Verifiers Standard Verifiers							

Web.config Options and Associated Resource File Parameters

This topic lists Web.config file options you can modify to enable, disable, or customize features.

For more information about the event options, refer to the *Brainware Intelligent Capture Scripting Guide*.

Option	Description
ADOCmdExecutionTimeOut	Defines the timeout, in seconds, for executing stored procedures in the database. Possible values Any valid integer
AllowAccessToDocumentsToIndexOnly	For more information, see About Navigation to Documents for Indexing . Possible values True: Enable navigation to indexable documents only False: Enable navigation to out-of-workflow documents. The default value is False.
BatchViewPageSize	Defines the number of batches per page that display in the Web Verifier batch list. Possible values Any valid integer The default value is 20.
client script mode	Defines the parameter to compress the script file that is sent to the browser from the server. Possible values Test: Testing or debugging of Web Verifier client side script on browser. Release: Used in production environment to minimize the file

Option	Description
	size of the client side script that assists in improving page loading performance.
cacheScripts in the <clientScript> element	<p>Defines the Ext. script caching behavior.</p> <p>Possible values</p> <p>True: Used in <i>Ext.Loader.setConfig</i> parameter to enable caching.</p> <p>False: Used in <i>Ext.Loader.setConfig</i> parameter to disable caching.</p>
ClientSideDocumentCacheSize	<p>Defines the number of pages to cache in the current document.</p> <p>Possible values</p> <p>Any valid integer</p> <p>The default value is 0.</p>
connectionStrings	The database connection string.
convertedScriptCaching	<p>Add this configuration in the <project.controller>\<project> node along with <i>mpdDistance</i> and <i>mpdThreshold</i>.</p> <p>Possible values</p> <p>True: Enables script conversion caching to reduce initial project loading time.</p> <p>False: Disables script conversion caching to slow down initial project loading time.</p> <p>The default value is True.</p> <p>Note: You also need to set this value to "true" in the <i>Brainware.system.project.exe.config</i> setting to enable script conversion caching.</p>
DialogWidth	<p>Defines the default width, in pixels, of message boxes in Web Verifier.</p> <p>Possible values</p> <p>Any valid integer</p> <p>The default value is 400.</p>
document cacheSize in the <document.controller> element	Specifies the number of workdoc objects to pre-load. This accelerates opening documents within the batch.

Option	Description
	<p>You cannot disable pre-loading, but minimize the number of pre-loaded documents to 2, that means one current and one pre-loaded.</p> <p>Possible values Any valid integer</p> <p>The default value is 5.</p>
<p>document maxPagesToPreload in the <document.controller> element</p>	<p>Defines the number of document pages to pre-load.</p> <p>First and last pages always pre-load, and remaining cache slots fill with pages that have field candidates starting from the lower index.</p> <p>The following actions take place on page images when a document loads in the background.</p> <ul style="list-style-type: none"> • Pre-load the page • Convert the page to PNG • Save the page to the database <p>Possible values Any valid integer</p> <p>The default value is 5.</p>
<p>DocumentViewPageSize</p>	<p>Defines the number of folders for Verifier to display in the document tree view when using Show Selected Batch mode. Additional batches display in subsequent navigation panels.</p> <p>Possible values Any valid integer</p> <p>The default value is 10.</p>
<p>EnableProfiler</p>	<p>Whether to enable the Web Verifier profiler.</p> <p>The profiler collects and records the duration of user actions, such as commands and their internal sub-operations.</p> <p>Possible values True / False</p> <p>The default value is False.</p>
<p>externalGroupIdColumn</p>	<p>Whether the external group ID column displays in Web Verifier.</p> <p>Possible values True / False</p>

Option	Description
	The default value is False.
externalBatchNameColumn	<p>Whether the external batch name column displays in Web Verifier.</p> <p>Possible values True / False</p> <p>The default value is False.</p>
focusChanged	<p>Whether to enables the focusChanged event for fields in the verification view.</p> <p>The event triggers when the user presses the Enter key in a field.</p> <p>The setting has no effect on the FocusChanged event if the <mouseClicked> attribute is set to true.</p> <p>Possible values True / False</p> <p>The default value is True.</p>
HelpLink	Links to Web Verifier Help.
httpHeaderBasedSso	Controls the single sign-on (SSO) user authentication mode.
login header in the <httpHeaderBasedSso> element	<p>Corresponds to the HTTP header attribute name that contains the SSO authenticated user name.</p> <p>The SSO service uses this attribute to send the user name.</p>
Enabled in the <httpHeaderBasedSso> element	<p>Whether to use the Web Verifier SSO feature.</p> <p>Possible values True / False</p> <p>The default value is False.</p>
sessionHeader in the <httpHeaderBasedSso> element	The provider-dependent name of the HTTP header that the SSO service uses to send the user session ID.
inactiveUserTimeout	<p>Unchangeable attribute.</p> <p>Note: This attribute does not control the user session timeout. The <sessionState Timeout> parameter controls the user session timeout.</p>

Option	Description
inspectionTimeOut	Unchangeable attribute. Note: This attribute does not control the user session timeout. The <code><sessionState Timeout></code> parameter controls the user session timeout.
instanceName	The instanceName value displays in the batch list column "Last Module". Note: The instanceName value must be unique across all installed Web Verifier servers accessing the same database.
itemCopied	Whether to enable the itemCopied event. Possible values True / False The default value is False.
LanguageDisplayName_ <i>[ISO]</i>	Customizes the language display names in the language selection menu. Replace <i>[ISO]</i> by the three letter directory name in <i>[Installation path]\Brainware Intelligent Capture Web Server\Bin\Resources</i> . Example for Simplified Chinese <pre><add key="LanguageDisplayName_ZHO" value="中文简体"/></pre>
level	Defines the tracing level. Possible values DEBUG: Trace all information and error messages. ERROR: Trace error messages only.
loadInSeparateProcess	Unchangeable attribute.
mouseClicked	Whether to enable the mouseClicked event on fields and tables in the verification view in indexing mode. Possible values True / False The default value is False.

Option	Description
pathToProjectExe	<p>The location of the Designer program Brainware.System.Project.exe. In typical installations, it is not required to modify this value.</p> <p>Possible values</p> <p>A valid non-UNC path ending with a “\”.</p> <p>The default value is <i>[Installation path]\Brainware Intelligent Capture\Bin\</i>.</p>
ReinitScriptEngineAfterScriptErrors	<p>Whether to recover the script engine after a script error in Web Verifier.</p> <p>Possible values</p> <p>True / False</p> <p>The default value is False.</p>
remoteObjectRenewalTimeout	<p>Defines, in seconds, the time to lapse before renewing remote object references. The lower the number the faster unused objects free memory. Increase this value in the event of errors caused by long-running commands, such as field validation.</p> <p>Possible values</p> <p>Any valid integer more than or equal to 30.</p> <p>The default value is 30.</p>
SavePageImageToDatabase	<p>Specifies if page images extracted from document file blobs needs to be saved back to the database.</p> <p>Possible values</p> <p>True / False</p>
timeout in the <sessionState> element	<p>Defines, in minutes, the amount of time a user can be inactive before the session ends.</p> <p>Specify a value less than that of the SSO session. For details, see the product documentation of your SSO provider.</p> <p>Possible values</p> <p>Any valid integer.</p> <p>The default value is 20.</p>
ShowExtendedErrorMessage	<p>Whether to enable stack trace information for Web Verifier error messages.</p> <p>Error messages display in the trace log file.</p> <p>Possible values</p>

Option	Description
	<p>True / False</p> <p>The default value is False.</p>
slogan	<p>A text message that displays on the Web Verifier browser header, such as corporate messages, announcements, or the corporate slogan.</p> <p>Possible values</p> <p>The default value is an empty string.</p> <p>Example</p> <pre data-bbox="727 661 1317 741"><verifier.webclient> <company slogan="This is a slogan" /></pre>
SYSTEM_LONG_DATE_FORMAT	<p>The XML key available in each Brainware.Verifier.WebClient.resx file located in <i>[Installation path]\Brainware Intelligent Capture Web Server\Bin\Resources\[/language code]</i>.</p> <p>The key contains the date pattern for the last access date column in the batch list for the respective language.</p> <p>To use the default system date pattern, leave the value element empty. The time format uses a 24-hour clock.</p> <p>For Traditional and Simplified Chinese, use the date format in the following example without any Chinese characters.</p> <p>Example for Chinese</p> <pre data-bbox="727 1186 1300 1371"><data name="SYSTEM_LONG_DATE_FORMAT" xml:space="preserve"> <value>yyyy-MM-dd, hh:mm:ss</value> </data></pre>
transactionIdColumn	<p>Whether the transaction ID batch column displays in Web Verifier.</p> <p>Possible values</p> <p>True / False</p> <p>The default value is False.</p>
transactionTypeColumn	<p>Whether the transaction type batch column displays in Web Verifier.</p> <p>Possible values</p> <p>True / False</p>

Option	Description
	The default value is False.
tabPressed	Whether to enable the tabPressed event on fields and tables in the verification view in indexing mode. Possible values True / False The default value is False.
tableCellSelected	Whether to enable the tableCellSelected event. Possible values True / False The default value is False.
usePath	Possible values True: Use the pathToProjectExe parameter. False: Use the current directory instead of the pathToProjectExe parameter. The default value is True.
waitLoadTimeOut	Defines the timeout for the initial loading of the project.exe.

About Navigation to Documents for Indexing

Indexable documents are documents with states from enabled workflow input states. The Web.config option `AllowAccessToDocumentsToIndexOnly` and the Web Verifier option "Disable navigation to valid documents" control the navigation to indexable documents.

Example

Workflow settings: 550 -> 700

A batch includes documents with states 550, 600, and 700.

If you set `AllowAccessToDocumentsToIndexOnly` to `True` and activate the "Disable navigation to valid documents" option in Web Verifier, you cannot access documents with state 600 or 700.

Enable Navigation to Indexable Documents

To enable navigation to indexable documents only, complete the following steps.

1. From the `[Installation path]\Brainware Intelligent Capture Web Server` directory, open **Web.config** in a text editor.
2. Search for `<appSettings>`.

3. Add the following line.

```
<add key="AllowAccessToDocumentsToIndexOnly" value="true" />
```
4. Save and close the file.
5. In Web Verifier, activate the **Disable navigation to valid documents** option.

Registry Options

You can create or modify the following keys in the Windows registry to enable, disable, or customize features.

Key	Description
ErrorTraceDir	Provides the possibility to change the component log file location. The setting does not affect the core product log file location.
HideBatchReleaseDialog	<p>Allows you to enable or disable the Batch Release dialog box within Verifier, where the workflow does not require prompting users to the next task. The registry value determines the next action carried out by users.</p> <p>The default action of the Batch Release dialog box is to verify the next invalid batch. When BIC suppresses the dialog, this value is maintained. To change to a different action, use the Batch Release dialog box once, then change the setting accordingly and click OK.</p> <p>The default value is 0.</p>
ErrorTrace - All	<p>Defines the trace level.</p> <p>The default value is 1.</p>
MaximumDiskspaceUsageMB	Defines the disk space in MB allocated for component level logs.
TotalDaysToKeepFiles	Defines the number of days the BIC server retains the component log files.

Create the Registry Key *ErrorTraceDir*

To create the registry key, complete the following steps.

1. In **Windows Registry Editor**, complete one of the following substeps.
 - For a 32-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Hyland_BW\ErrorTrace*.
 - For a 64-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Hyland_BW\ErrorTrace*.
2. In the right pane, right-click and then click **New > String Value**.
3. In the **Name** field, type `ErrorTraceDir` and then click **OK**.
4. Right-click the **ErrorTraceDir** key and then click **Modify**.
5. In the **Edit String** dialog box, in the **Value data** field, type the path and then click **OK**.

Note: The path must exist and the service account / user needs write permission to the path.

- Restart all BIC applications and services.

Create the Registry Key *HideBatchReleaseDialog*

To create the registry key, complete the following steps.

- In **Windows Registry Editor**, complete one of the following substeps.
 - For a 32-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Hyland_BW\Cedar*.
 - For a 64-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Hyland_BW\Cedar*.
- In the right pane, right-click and then click **New > DWORD (32-bit) Value**.
- In the **Name** field, type `HidebatchReleaseDialog` and then click **OK**.
- Right-click the **HidebatchReleaseDialog** key and then click **Modify**.
- In the **Edit DWORD (32-bit) Value** dialog box, in the **Value data** field, complete one of the following steps and then click **OK**.
 - To display the confirmation screen, type zero: 0.
 - To hide the confirmation screen, type 1.
- Restart all BIC applications.

Modify the Registry Key *ErrorTrace - All*

To modify the value, complete the following steps.

- In **Windows Registry Editor**, complete one of the following substeps.
 - For a 32-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Hyland_BW>ErrorTrace*.
 - For a 64-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Hyland_BW>ErrorTrace*.
- In the right pane, right-click **All** and then click **Modify**.
- In the **Edit DWORD (32-bit) Value** dialog box, in the **Value data** field, complete one of the following steps and then click **OK**.
 - To turn off logging, type 0.
 - To log only errors, type 1.
 - To log errors and warnings, type 2.
 - To log errors, warnings, and information, type 3.

Create the Registry Key *MaximumDiskSpaceUsageMB*

To create the registry key, complete the following steps.

- In **Windows Registry Editor**, complete one of the following substeps.
 - For a 32-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Hyland_*

BW\ErrorTrace .

- For a 64-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Hyland_BW\ErrorTrace* .
2. In the right pane, right-click and then click **New > DWORD (32-bit) Value**.
 3. In the **Name** field, type *MaximumDiskSpaceUsageMB*.
 4. Right-click the **MaximumDiskSpaceUsageMB** key and then click **Modify**.
 5. In the **Edit DWORD (32-bit) Value** dialog box, in the **Value data** field, complete one of the following steps and then click **OK**.
 - To deactivate the option, type zero: 0.
 - Type the appropriate value in megabyte.

Create the Registry Key *TotalDaysToKeepFiles*

To create the registry key, complete the following steps.

1. In **Windows Registry Editor**, complete one of the following substeps.
 - For a 32-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Hyland_BW\ErrorTrace* .
 - For a 64-bit machine, navigate to *HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Hyland_BW\ErrorTrace*.
2. In the right pane, right-click and then click **New > DWORD (32-bit) Value**.
3. In the **Name** field, type *TotalDaysToKeepFiles*.
4. Right-click the **TotalDaysToKeepFiles** key and click **Modify**.
5. In the **Edit DWORD (32-bit) Value** dialog box, in the **Value data** field, complete one of the following steps and then click **OK**.
 - To deactivate the option, type zero: 0.
 - Type the number of days.